

3.29 – Send logs to syslog

SparkView can collect and forward logs under Linux via syslog. This requires a few adjustments on the part of SparkView and on the server.

Adjustments SparkView:

Create the file `logging.properties` in the SparkView root directory. You can also copy an existing one from the JRE/lib directory and customize it by adding the following lines at the end:

```
.level= INFO
handlers= java.util.logging.ConsoleHandler, com.agafua.syslog.SyslogHandler
# Syslog logger
com.agafua.syslog.SyslogHandler.transport = udp
com.agafua.syslog.SyslogHandler.facility = local0
com.agafua.syslog.SyslogHandler.port = 514
com.agafua.syslog.SyslogHandler.hostname = vmuser-xubuntu1604
```

Then add the Java VM argument to the command that starts SparkView:

```
-Djava.util.logging.config.file=yourSparkViewFolder/logging.properties
```

Adjustments Server (Ubuntu):

1. Edit the file `/etc/rsyslog.conf` and comment/activate the following two lines:

```
module(load="imudp")
input(type="imudp" port="514")
```

2. Go to the directory `/etc/rsyslog.d` and create a new file `"60-java.conf"` (the name can be chosen arbitrarily) with the following content:

```
local0.* /var/log/gateway.log
```

3. Restart the syslog service: `sudo service rsyslog restart`

Revision #2

Created 18 March 2024 07:55:24 by Julian

Updated 3 September 2024 11:08:00 by Julian